

PWOTEJE TÈT OU KONT GRIP ZWAZO H5N1

Wete ekipman pwoteksyon pèsonèl sou ou san danje
nan sal pou tire lèt yo

Sa pou w konnen anvan w retire ekipman pwoteksyon pèsonèl (Personal Protective Equipment, PPE)

- Pale avèk sipèvizè w pou konnen si sa aplike pou ou
- Retire PPE a anvan w antre nan nenpòt zòn pwòp tankou twalèt, sal poz, ak nan zòn administratif yo
- Mete sou kote PPE ki ka resèvi yo pou netwayaj ak dezenfeksyon epi jete PPE jetab ou dapre direktiv patwon an

Retire PPE nan lòd sa a:

1. Retire gan travay ekstèn, si w mete yo 
2. Rense lejèman deyò rad yo (kovèti bòt oswa bòt ak tabliye) 
3. Retire kas di, si w mete youn 
4. Retire kovèti bòt oswa bòt 
5. Retire tabliye a manch 
6. Retire pwotèj figi, si w mete youn 
7. Retire kouvèti tèt oswa kouvèti cheve 
8. Retire linèt pwoteksyon yo 
9. Wete respiratè 
10. Retire gan jetab yo 
11. Lave men w ankò pandan 20 segonn avèk savon ak dlo oswa, si savon ak dlo pa disponib, itilize yon dezenfektan pou men abaz alkòl 

Apre w fin retire PPE:

- Pa sèvi ak PPE ki ka resèvi yo jiskaske yo netwaye epi dezenfekte kòrèkteman
- Netwaye epi dezenfekte PPE ki ka resèvi yo selon direktiv patwon w bay
- Si sa posib, pran yon douch nan travay ou apre chif travay ou epi mete rad pwòp. Si pa gen douch nan travay la, netwaye w otank posib, mete rad pwòp sou ou, epi ale toudwat nan douch lè w sot nan travay.
- Kite tout rad ak ekipman ki kontamine yo nan travay la pou yo ka netwaye



U.S. CENTERS FOR DISEASE
CONTROL AND PREVENTION

ESKANE POU
APRANN
PLIS →

